

# Documentation: Installation and Implementation of OpenPose on Windows 10

Prepared by: Lim Jun Jie

# This documentation had been prepared by assuming you had installed the dependencies of tensorflow-gpu and CUDA. If you haven't install them, please refer to my github link for more information ( <https://github.com/JJLim99/Implementation-of-TensorFlow-GPU-CUDA-in-Windows.git> )

# The code is tested using tensorflow-gpu=1.15 and keras=2.3.1, AMD Ryzen 5 3550H, 12GB RAM, GTX 1650

## Part 1: Installation of OpenPose

1. Open cmd, go to your desired location path and clone the repository


```
git clone https://github.com/ildoonet/tf-pose-estimation.git
```

2. Install Swig for Windows

- Click the link below to download Zip file of Swig

```
https://jaist.dl.sourceforge.net/project/swig/swigwin/swigwin-3.0.12/swigwin-3.0.12.zip
```

- Extract the Zip file to any location. ( For example: C:\swigwin-3.0.12 )
- Add the path of Swig into the *environment variables* (For both of the *User variables* for Owner and *System variables*)




# For adding the path of Swig, go to Advanced System Settings > Environment Variables,

- i. Click the Environment Variables (Red box)
  - ii. Double click the Path for user variables for Owner (Blue box)
  - iii. In the Edit environment variables, click New then paste the path of Swig. (Green box)
  - iv. Then click OK at Edit environment variable (Purple box)
  - v. Repeat step ii. until iv. For the Path at System variables (Orange box)
  - vi. Finally, click OK for the confirmation. (Black box)
- After that, go back to cmd and type the code below to verify the installation

```
swig -version
```

Example of the output is shown as below:



```
Microsoft Windows [Version 10.0.18363.1016]
(c) 2019 Microsoft Corporation. All rights reserved.

C:\Users\Owner>swig -version

SWIG Version 3.0.12

Compiled with i686-w64-mingw32-g++ [i686-w64-mingw32]

Configured options: +pcre

Please see http://www.swig.org for reporting bugs and further information

C:\Users\Owner>
```

- Go back to the location path of your main repo, and type the following command

```
cd tf_pose/pafprocess
swig -python -c++ pafprocess.i && python setup.py build_ext --inplace
```

### 3. Download the CMU's model graphs.

- Go to <path\_to\_repo>\tf-pose-estimation\models\graph\cmu, double click download.sh

- Installation will be initiated automatically
- graph\_opt.pb will be downloaded

#Alternative:

- Go to the same path location as previous method by using cmd, then type  
`bash download.sh`
- graph\_opt.pb will be downloaded

## Part 2: Demo of OpenPose

1. Open cmd and go to the path of the repo, and type the following command to try with saved video.

```
python run_webcam.py --video <path to video.mp4>
```

2. Open cmd and go to the path of the repo, and type the following command to try with your own webcam.

```
python run_webcam.py --model=mobilenet_thin --resize=432x368
```

# value of model and resize is optional

# ( **Optional** ) If you have error by running the original python scripts of the original repo, you can download my github link as I had modified some codes to be compatible with my dependencies.

```
My github link: https://github.com/JJLim99/OpenPose.git
```